

# Firmware Release Note

<b>Model : CLP-365W, 366W</b>	<b>Date :</b>	<b>September 27, 2018</b>
-------------------------------	---------------	---------------------------

<b>Version</b>	<b>Category</b>	<b>Change Description</b>
<b>V3.00.02.05</b> (12-Dec, 2013)	Fix Defect	Fixed the imaging unit error
<b>V3.00.02.07</b> (15-Apr, 2014)	Fix Defect	Improvement of Color to Mono Printing Problem
		Fixed Google Cloud Print issue. ("chunked" data control)
		Changed the target temperautre for improvement of Naonodust
<b>V3.00.02.16</b> (22-Dec, 2014)	Add Func.	Add Error Code (M3-1112, Jam Inside of Machine)
	Fix Defect	Compatibility of OTG cable
		Fix initialization issue of user setting vlaues when f/w is upgraded
		[Google Cloud Print] Fix to the latent issue and enhancement to UI
		Fix USB PC printing blocking problem
		[Google Cloud Print] Error page is getting printed when given JPEG/TXT print job.
<b>V3.00.02.19</b> (20-Aug, 2015)	Add Func.	Apply to Samsung Cloud Print

## ※ Note

- Please do not turn off the printer and your computer until firmware update finishes.
- If you are using USB connection, disconnect all other USB printers from the PC.
- The firmware update you are about to install has been tested for compatibility with Samsung toner cartridge products ONLY.  
Installing The upgrade may cause a non-Samsung toner cartridge to malfunction.
- Do not run your printer during the firmware update.(Do not have any print job)

## Update Procedure

1. Make sure that the machine is connected to the PC with a USB cable or network
2. Make sure that the current f/w version of your printer.

Press and hold 'Cancel' button for about 2seconds until the green LED blinks slowly, and then release it

Configuration Report will be printed out, Check the f/w version.



If the firmware version is V3.xx.01.xx, Execute CLP365W\_Upgrade\_Patch.exe

And then patch rom will be download on the machine.

Please wait until green LED is ON.(About 2 minute)

\* LED Status

- 2.1) Red LED Blinking for about 30 sec
- 2.2) Green LED ON for 30 sec
- 2.3) Red LED Blinking for 60 sec
- 2.4) Green LED ON

If the firmware version is V3.xx.02.00 and more higher, Go to No.3 Step.

3. Run firmware file(CLP365W\_V3.00.02.16.exe)
4. The firmware update will start.  
Once the firmware update is complete, the machine will be rebooted automatically.